Drill Core Library: Instructions for WFS service use through QGIS

- 1. Open QGIS and add a base map of your choosing.
- 2. Navigate to Layer > Add Layer > New WFS Layer.



3. The following dialogue box will appear.

Q	Data Source	Manager WFS / OGC API - Feature	25		×			
	Browser	Server Connections						
V	Vector	Landmælingar			•			
θ,	Raster	Connect New I	Edit Remove	Load	Save			
	Mesh	Filter						
0:	Point	Title	 Name 	Abstract S	al 🔷			
€÷	Cloud	Þéttbýlisstaðir	Hagstofan: the ttby lisstadir	Viõmiõunardagsetni				
	Delimited Text	Þjónusta	ferdamalastofa:thjonusta	Upplýsingar um sta				
, ⊅ <u>∎</u>		Örnefni, þéttleiki eftir reitum	LMI_vektor:v_ornefni_grid	Sýnir þéttleika örne				
	C	Örnefni, þéttleiki	IS_50V:v_ornefni_klasi	Sýnir þéttleika örne				
	GeoPackag	Íslendingasögur	ferdamalastofa:isl_stadir_sogur	Staðir sem nefndir e				
1	Spatial ite	Áningarstaðir	ferdamalastofa: aningarstadir	Áningarstaðir víðsve				
-	oputatite	WetlandArea	ERM:WetlandArea	EuroRegionaMap(E				
65	PostgreSQ	Well	ERM:Well	EuroRegionaMap(E				
		WaterfallPointConnectionPoin	nt ERM:WaterfallPointConnectionPoir	nt EuroRegionaMap(E				
<u> </u>	MSSQL	WaterfallLine	ERM:WaterfallLine	EuroRegionaMap(E				
	Oracle	WatercourseLine	ERM:WatercourseLine	EuroRegionaMap(E				
-	Oracle	WatercourseArea	ERM:WatercourseArea	EuroRegionaMap(E				
	Virtual	Viökomustaðir	ferdamalastofa:vidkomustadir	Upplýsingar um sta				
R.	Layer	Virkjanir	orkustofnun:gisvirkjun					
	SAP	virkar_skyndilokanir	fiskistofa:virkar_skyndilokanir					
	HANA	virkar_reglugerdir	fiskistofa:virkar_reglugerdir		-			
-	W/MS/	4			•			
	WMTS	Use title for layer name						
		Only request features overlapping	the view extent					
970	WFS /							
	OGC API	Coordinate Reference System						
	WCS	EPSG:3057			Change			
	XY7 -			Build query Close Add	Help			

4. Under Server Connections, click New. The following dialogue box will appear. Enter the name and URL shown in the image below (or any name you prefer), then click OK.

300	ma Ní kart						
Name N2-Korq							
RL	https://kort.ni.is/geoserver/wfs hentication						
uthe							
Con	figurations Basic						
Choo	se or create an authent	ication configuration					
Ma	Authentientien						
NO A	Authentication +						
Confi	inurations store encrypt	ed credentials in the O	GIS authentication (latabase.			
WFS Options							
13 0	puons						
Versi	on	Maximum	•	Detect			
Versi Max.	on number of features	Maximum	•	Detect			
Versi Max.	on number of features inable feature paging	Maximum	•	Detect			
Versi Max. Versi Max.	on number of features inable feature paging size	Maximum	•	Detect			
Versi Max. Versi Max. E Page	on number of features inable feature paging size	Maximum	•	Detect			
Versi Max. Versi E Page	on number of features nable feature paging size gnore axis orientation (V	Maximum VFS 1.1/WFS 2.0)	•	Detect			
Versi Max. Versi Max. E Page Ig	on number of features inable feature paging size gnore axis orientation (V nvert axis orientation	Maximum	•	Detect			
Versi Max. Versi Max. E Page Iq Iq	on number of features inable feature paging size gnore axis orientation (V nvert axis orientation	Maximum WFS 1.1/WFS 2.0)	•	Detect			
Versi Max. Versi Max. E Page Ig Ig	on number of features inable feature paging size gnore axis orientation (V nvert axis orientation lise GML2 encoding for tr	Maximum WFS 1.1/WFS 2.0)	•	Detect			
Versi Max. Versi Max. E Page Ig Ir	number of features inable feature paging size gnore axis orientation (V nvert axis orientation ise GML2 encoding for tr	Maximum WFS 1.1/WFS 2.0)	• [Detect			
Versi Max. Versi Max. E Page I I I I I U	on number of features inable feature paging size gnore axis orientation (V nvert axis orientation lise GML2 encoding for tr	Maximum WFS 1.1/WFS 2.0)	• .	Detect			
Versi Max. ✓ E Page I I I U	on number of features inable feature paging size gnore axis orientation (V nvert axis orientation ise GML2 encoding for tr	Maximum Maximum NFS 1.1/WFS 2.0)	•	Detect			
Versie Max. ✓ E Page I I I I U	number of features nable feature paging size gnore axis orientation (V nvert axis orientation ise GML2 encoding for tr	Maximum WFS 1.1/WFS 2.0)	•	Detect			
Versi Max. ✓ E Page I I U	number of features nable feature paging size gnore axis orientation (V nvert axis orientation lse GML2 encoding for tr	Maximum WFS 1.1/WFS 2.0)	•	Detect			
/ersi /ax. ✓ E age I I I	number of features nable feature paging size gnore axis orientation (V nvert axis orientation ise GML2 encoding for tr	Maximum WFS 1.1/WFS 2.0) ransactions	•	Detect			

5. Select NÍ-kort (or the name you assigned) from the dropdown menu under Server Connections and click Connect. Select the layer "drillcore_wfs_export" and click Add to add it to your map.

Data Source	Manager WFS / OGC API - Features						
Browser	Server Connections						
Vector	NÍ-kort						
Raster	Connect New Edi	Remove	Load Save				
Mesh	Filter						
Point	Title	▼ Name	Abstract Sql				
Cloud	Smadyr_dreifing	ni:Smadyr_dreifing	Gagnasafn hjá Nátt				
Delimited	ni_jardlog	ni:ni_jardlog					
Text	island-haed	ni:island-haed					
	ISL IINH 1:500k Bedrock Age	IINH_Geology:ISL_IINH_500k_BA	The 1:500,000 Geol				
Беораскас	is_yfirlit	ni:is_yfirlit					
Spatial ite	drillcore_wfs_export	ni:BorkjarnarNI	Borkjarnar í safni N				
opullatile	dreifing	ni:Floraisl_dreifing					
PostgreSQ	dlin_allt	ni:dlin_allt					
	bioice_Synatokustadir_1991_20	04_WG ni:bioice_Synatokustadir_1991_2004	4_WG All sampling sites o				
MSSQL	Biolce Landmass	ni:bioice_land_WGS84	Countries that span				
Oracle	bioice Bathymetrie	ni:bioice_dlin_WGS84	Bathymetrie (depth				
Olacie	bio_ice_dist	ni:bio_ice_dist					
Virtual Layer							
SAP HANA							
WMS/ WMTS	Use title for layer name						
WES /	✓ Only request features overlapping the	view extent					
OGC API	Coordinate Reference System						
 WCS	EPSG:4326		Change				
			Build query Close Add Help				



6. You can now use the Identify tool (just below and to the right of the Help menu in this image) to select and learn more about any drill core.



Key to attribute fields

- Audkenni: Well ID, a five-digit number assigned by the National Energy Authority and catalogued in their Well Registry (<u>https://orkustofnun.is/borholuleit</u>).
- Borholunafn: Name of the borehole. A non-unique code assigned to each well, usually during drilling.
- Fjoldi_kassa: Number of boxes of core stored in the IINH Drill Core Library.
- Svaedisnafn: Name of the area where the borehole is located. From NEA Well Registry.
- Upphafsar: Year when drilling began. From NEA Well Registry.
- Dypi: Total depth of borehole. From NEA Well Registry.
- Tilgangur borunar: Purpose of drilling. From NEA Well Registry.
- Slod: Hyperlink to well entry in the NEA Well Registry.

